Active Directory (AD) is a core component of Microsoft's Windows Server environment that provides centralized management of users, computers, and network resources. It enables administrators to organize and control access to information, enforce security policies, and streamline network administration across an organization.

Setting up Active Directory is a crucial step in building a secure and efficient IT infrastructure. It allows organizations to manage authentication, authorization, and directory-based services through a single, unified system. Whether you're deploying it in a small business or a large enterprise, understanding the setup process ensures a stable and scalable environment.


This guide provides a **step-by-step walkthrough** for installing, configuring, and verifying Active Directory Domain Services (AD DS) on a Windows Server. By following these steps, you will learn how to:


- Prepare your server environment for AD installation
- Install the Active Directory Domain Services role
- Promote the server to a domain controller
- Configure DNS and domain settings
- Verify and manage your new domain

By the end of this guide, you will have a fully functional Active Directory domain ready to manage users, groups, and network resources within your organization.


On the server, we first need to install the AD, this can be done on the server manager dashboard Click Manage>> add roles and features

follow the prompts by clicking next







Select "role based or feature based installation" and click next




Check box "Active directory domain services"




Check retart box and click install






Installation is complete.


Now we promote the server to a domain controller by taking the following steps




Select "add a foreste" and give a root domain name, then click next




Provide password and click next






Upon completion of installation, server will restart




CREATING ORGANISATIONAL UNITS

After servers has restarted, next step is to create organisational units


To do so, we select Tools>> active directory users and computers




Next, right click on root domain name, select new and click on organisational unit




Name your organisational unit and click ok. Replicate for as many organisational units as required




To create Groups, right click on Root domain>> new>> groups




Provide group name and click ok, create as many groups as required





In the same manner, we will also create users





Select password setting you require, for the purpose of this labs we will select passwords never expire (this is not best practice)







NETWORK CONFIGURATION


In this section we will be configuring the network.

From control panel>> Network and internet >> network and sharing center

Follow the steps in the image below









Select Static IP and provide the IP address of the PC (you can get the ip address by typing "ipconfig' in CMD)

preferred DNS server is the IP of the windows server, click OK




Next we add the system to the domain and sign in with the user account created


Right click on "MY PC" and click on properties




Select "system protection" on the left




Clock on computer name tab, then click change




Provide domain name and click OK




There will be a sign in pop up, sign in with name and password of user created Click okay and the system will restart






Once restarted, sign in as another user with the credentials of the user we created (Not the Local Admin account)



Confirm that PC domain name has changed and that you are logged in as the user created and not the local Admin of the PC







CREATING AND IMPLEMENTING A GROUP POLICY

We will be adding policies and linking them to groups and users.


On the windows sever manager dashboard, select tools and click Group policy management




Select company domain>> right click group policy object>> select new



Create a name for the GPO and click ok




Now, we right cick on the GPO we created and click on edit to add the policy




Depending on what we are trying to achieve, we can create the policy on either COMPUTER CONFIGURATION or USER CONFIGURATION, it can also be done on both.

Under Computer config, expand Policies, expand Adminstrative templates, select all settings.


Locate the setting requires(in this example, we will go with removing access to shutdown, restart, sleep and hibernate) the click on edit policy setting




Check Enable, click on apply and click OK




Repeat same steps for USER CONFIG




Confirm on GPO to see if policy was added




Next we link the GPO to our domain








Our next step is to enforce the policy




Then we add user to the policy









With that done, the policy is now active.

We can force the update manually on the users PC by running CMD "gpupdate /force" or simply boot the PC for it to take effect.

We can log in to confirm user has no access to shutdown or restart.

